Overview


| Prefab | Description | |
|-----------|--|--|
| Joysticks | | |
| Fixed | The fixed joystick is triggered by tapping and dragging the center of the controller. | |
| Floating | The joystick is triggered when dragging any bounded area. | |
| DPads | | |
| DPad | Simulates a directional pad to start moving at the moment of touch without having to drag. | |
| DPadX | A variation of the DPad for horizontal moves. | |
| DPadY | A variation of the DPad for vertical moves. | |
| Buttons | | |
| Button | Generic button template that can be used to create various other buttons. | |

Note: All the steps below assume that the project is using the new input system and has a control schema configured for GamePad.

Prefabs

The Prefabs can be found in /VirtualButtonsForUnity/Prefabs and need to be applied to a canvas in the scene.






Joysticks

Fixed and **Floating** joysticks have the same properties, additionally the Floating joystick has the properties "Centralize OnPointerUp" and "Hide OnPointerUp".

The **Joystick Fixed** stays in a fixed position, being necessary to touch and drag the central circle to start the movement. The **Floating Joystick** responds to any touch in the main area without having to hit its center.

When adding the Joystick, you must choose the GamePad Stick that will be represented by it in the "Stick Control Path" property:




DPad

Directional button that is activated by clicking on any position around the center and responds to being dragged from one direction to another.


When adding the Joystick, you must choose the GamePad Stick that will be represented by it in the "DPad Control Path" property:


Warning: You need to select the Stick Left or Right on Gamepad, the DPad type will not work.



DPadX and **DPadY** are a version of the standard directional pad using horizontal and vertical direction respectively.









If you choose not to use a Prefab and change the "direction" property on the DPad, you will need to change the image displayed in the interface on the handle object:



Button


When adding a button, you need to inform which button will be triggered by it in the "Control Path" property of the "On-Screen Button" component:





Then you must change the letter that will be displayed in the interface in the "Text" object:





Properties

Joystick(Fixed)

| Prop | Description |
|--------------------|--|
| Center Area | RectTransform from the center point of the joystick. |
| Handle | RectTransform of the object to be dragged |
| Movement Range | Range to the "On-Screen Stick" component. |
| Stick Control Path | Control path to the "On-Screen Stick" component. |

Floating Joystick

| Prop | Description | | | |
|-------------------------------|--|--|--|--|
| All props from Fixed Joystick | | | | |
| Hide OnPointerUp | When enabled, the joystick is kept hidden until the screen is touched and hidden again when releasing the touch. | | | |
| Centralize OnPointerUp | Joystick is re-centered in the initial position on release. | | | |

DPad

| Prop | Description |
|-------------------|---|
| Center Area | RectTransform from the center point of the joystick. |
| Handle | RectTransform of the object to be dragged |
| Movement Range | Range to the "On-Screen Stick" component. |
| DPad Control Path | Control path to the "On-Screen Stick" component. |
| | Warning: You need to select the Stick Left or Right on Gamepad, the DPad type will not work. |
| Direction | The direction that will be controlled Horizontal, Vertical or Both. |
| UI Movement Range | DPad movement to display a visual response. |
| Move Threshold | The minimum position in relation to the center for the movement to be executed. |
| Force Int Value | Forces performed moves to return -1, 0 or 1 |

Button

| Prop | Description |
|----------------|------------------------------|
| Rotation Limit | Rotation limit when pressed. |
| Rotation Speed | Rotation speed when pressed. |